



## CONSULT-III plus Installation Interrupted Message Version 201.2 or higher


1. Click “Restart” from the power options menu and hold down the “Shift” key at the same time.
2. Once the computer has rebooted, you will be able to choose the “Troubleshoot” option.



3. Select “Advanced options” and then “Startup Settings”.




4. Click “Restart” to modify configuration settings.



## CONSULT-III plus Installation Interrupted Message Version 201.2 or higher

5. Once the computer has rebooted, Press F7 on your keyboard to select “Disable driver signature enforcement”.



6. Your computer will reboot and install any drivers including the unsigned drivers.
7. Open CONSULT-III plus and retry the VI connection with the USB cable.